Datto BCDR Integration Setup

Setting up your Datto BCDR integration with MSPbots requires you to secure the Datto BCDR API URL, public key, and secret key and then enter these values when you connect Datto BCDR to MSPbots.

What's in this article:

- How to retrieve parameter values
- How to connect Datto BCDR with MSPbots

How to retrieve parameter values

Perform the following steps to set up the connection:

- 1. Log into the Datto Partner Portal.
- 2. Click the Admin tab, then select Integrations from the dropdown menu.
- 3. On the Integrations page, click the **BCDR** button at the top of the screen.
- 4. When the Business Continuity and Data Recovery integration information panes open, click the Enable API button in the top portion of the pane.
- 5. The Datto REST API is now enabled, and configuration options will now appear.

R NETWORKING CONNECTWIS	E AUTOTASK KASEYA	
usiness Continuity and Dat	a Recovery	
est API		
est API atto's new Rest API allows third partie ith Datto's Rest API provides readily a	s to create a dynamic user experience in a more reliable and scalable way. Creating an integration railable device and status information, which can be used by many third party applications such as	DISABLE API
Lest API atto's new Rest API allows third partie ith Datto's Rest API provides readily a SA, RMM, and Documentation type sol	s to create a dynamic user experience in a more reliable and scalable way. Creating an integration valiable device and status information, which can be used by many third party applications such as utions. Speak to your vendor about integration with Datto devices.	DISABLE API
test API atto's new Rest API allows third partie tht Datto's Rest API provides readily a SA, RMM, and Documentation type sol sst API Public Key:	is to create a dynamic user experience in a more reliable and scalable way. Creating an integration valiable device and status information, which can be used by many third party applications such as utions. Speak to your vendor about integration with Datto devices.	DISABLE API

Use the Rest API Public Key as Public Key
Use the Rest API Secret Key as Secret Key.

How to connect Datto BCDR with MSPbots

1. Log in to the MSPbots app and navig					vigate	igate to Integrations.									
	M	spaörs	¢ 🚺	NFR		1	Refer and Earn	Φ	Client: MSPbots.ai	Forum	KB Help Center	Request New Feature	ж (
	>														
	ß	Daily Total Escalation		Daily Total Messages		Escalated Message	•	Wel	come to MSPbots!						
	ዪ	Ó		0		5		MORE	AUTOMATION MORE PROFIL	hang	Muslash	A BLANA	h 11		
	88	Weekly 0		Weekly 0		Weekly 5									
	1								onic		-				
	⊞	7 days generated	messages	s by bots (Bots with es	scalation)			7 Day	s generated messages	by user (Bo	ots with escalati	ion)			
	٢														
	Ŀ														
	P														
	B														
	og 🔇			No Data						N	lo Data				
	٢			Click here to get mo	re details				(Click here t	to get more de	tails			
	\$														

- 2. Search for Datto Backup and open it.
- 3. Enter the following required fields:
 - API URL The default value is api.datto.com. Refer to Datto's documentation Using the Datto REST API With Datto device Integrations for more information.
 - Public Key

datto	Datto Backup	≈ ⊘ …
	* API URL :	
	Please Enter API URL	
	* Public Key :	
	Please Enter Public Key	
	* SecretKey :	
	Please Enter SecretKey	
	Save And Sync	
hen r	connecting Datto BCDR to MSPhots	

Refer to Step 5 in How to retrieve parameter values.

4. Click Save and Sync.